



TeacherFly

Controlled Beta User Guide

Version 1.9 | Updated 24 October 2026

Purpose A practical guide for invited TeacherFly Controlled Beta testers. It explains how to create and manage social media and marketing content packs, including the current workflow, key controls, downloads, Library, Teleprompter, preview features and troubleshooting steps.

Support: support@teacherfly.app

Spend less time creating social media and marketing content. Spend more time focused on your teaching.

Contents & Quick Start

1. Getting Started
2. Creating a Content Pack
3. Platforms, Formats and Recommendations
4. Audience, CEFR and Grammar Mode
5. Tone, Hook and CTA
6. Subtitles and Translation
7. Understanding Your Content Pack
8. Worksheets and Downloads · updated
9. Library and Teleprompter · updated
10. Account, Settings, Credits and Storage · updated
11. Batch Studio: Create, Retry, Preview and Worksheets
12. Repurpose Content: Create, Preview and Library
13. My Plan & Billing: plans, usage, upgrades and cancellation
14. Troubleshooting · updated
15. Beta Feedback and Support
16. Install TeacherFly on Your Phone (PWA) · new

Quick start

Create: Select teaching and platform settings, then generate your Content Pack.

Batch: Enter 2-5 topics; review and retry each pack independently.

Worksheets: Automatic for Single Pack; manual creation for Batch ready packs.

Library: Find packs by Worksheet or Repurpose asset status.

Billing: Compare plans, review credits and manage subscriptions with Paddle.

Support: support@teacherfly.app

01 / CONTROLLED BETA

Getting Started

TeacherFly Controlled Beta is for approved or invited testers. Sign in using the method provided with your Beta access instructions.

- TeacherFly supports email/password sign-in and Google sign-in.
- When signed out, TeacherFly shows the Welcome screen. Once signed in, the Create workspace and account controls become available.
- By signing in or using TeacherFly, you agree to the Terms of Service and acknowledge the Privacy Policy. Controlled Beta accounts are for users aged 18+.

If sign-in is required Sign in again before generating content. Your generation settings should be preserved where possible.


The image shows the TeacherFly sign-in interface. At the top, there's a 'TeacherFly Login:' section with an 'Email' input field, a 'Password' input field with a 'Show' toggle, a 'Login' button, and a 'Forgot password?' link. To the right is a 'Sign in with Google' button. Below this, a small line of text states: 'By signing in or using TeacherFly, you agree to the Terms of Service and acknowledge the Privacy Policy.' The main area is a large blue box with the text 'Welcome to TeacherFly.' and 'Let's create content that helps more students discover your teaching.'

Figure 1. TeacherFly sign-in screen.


The image shows the TeacherFly signed-in interface. At the top, there's a 'Logged in as: test@teacherfly.com' label and a 'Logout' button. Below this, a large blue box contains the text 'Welcome back, Test Teacher.' and 'Let's create content that helps more students discover your teaching.'

Figure 2. Signed-in welcome area and Logout control.


02 / CONTROLLED BETA

Creating a Content Pack

Single Pack is the main creation workflow in the Controlled Beta.

1. Open Create and choose Single Pack.
2. Enter a clear Topic / Keywords prompt. Example used in this guide: “Should I use some or any?”
3. Set Subject, Learner Age and CEFR Level where applicable.
4. Choose Natural or Strict Grammar Mode.
5. Choose the target Platform, Content Format and duration/slides where applicable.
6. Choose Tone, Hook Style, CTA Style and Subtitle Language.
7. Open Advanced Settings only when you need learner first-language, cultural adaptation or a custom note.
8. Review the “Ready to Generate With” summary, then select Generate Content Pack.
9. Wait for generation to finish. Do not repeatedly click Generate while a request is already running.

Recommendation behavior TeacherFly may adjust recommendations such as duration when the selected platform or format changes.



Create Your Content Pack

 **Single Pack**  **Batch Mode**  **Preview**

 **TOPIC / KEYWORDS**

when to use 'this' and when to use 'that'

Figure 3. Start a Single Pack and enter the teaching topic.

AUDIENCE

SUBJECT: General English | LEARNER AGE: Children (6-12) | CEFR LEVEL: A2 Elementary

GRAMMAR MODE

Natural (selected) | Strict

Natural = conversational • Strict = exam-accurate

CONTENT STRATEGY

PLATFORM: TikTok | Instagram | **FB Reels** | RedNote | YouTube | Bilibili | LinkedIn | X

CONTENT FORMAT: Short Video | DURATION / SLIDES: 90s

Resolved setup: **FB Reels • Short Video • 90s** Aspect ratio: 9:16

CONTENT STYLE

TONES: Friendly & Encouraging | HOOK STYLE: Big Question | CTA STYLE: Follow/Subscribe

SUBTITLE LANGUAGE: Portuguese + English

Advanced Settings HIDE ▲

Figure 4. Configure audience, platform, format and content style.

READY TO GENERATE WITH:

Subject: **General English** • Age: **Children (6-12)** • Level: **A2 Elementary** • Grammar: **Natural** • Platform: **FB Reels** • Format: **Short Video** •

Duration: **90s** • Tone: **Friendly & Encouraging** • Hook: **Big Question** • CTA: **Follow/Subscribe** • Subtitle: **Portuguese + English** •

First Language: **Portuguese** • Cultural Adaptation: **Neutral (Global)**

Generate Content Pack

Figure 5. Review the generation summary before starting.

Copy Title | Copy Script | Copy Subtitles | Copy Caption | Copy Description | # Copy Hashtags | Copy Worksheet | Copy Visual Directions

Repurpose PREVIEW

Repurpose Content preview

Generating when to use 'this' and when to use 'that'...

Figure 6. Generation in progress.

Copy Title

Copy Script

Copy Subtitles

Copy Caption

Copy Description

Copy Hashtags

Copy Worksheet

Copy Visual Directions

Repurpose

PREVIEW

HOOK • 0-15

When should you say the word this and when should you say that?

Vertical 9:16 framing. Friendly teacher speaks directly to camera with curious expression, displaying a simple text overlay reading 'This or That?' in upper safe area.

TEACH • 15-30

We use both words to talk about one person or thing. The distance from you changes which word you choose.

Medium shot of teacher showing two small markers on a desk to demonstrate distance, supported by clear graphic arrows pointing near and far.

TEACH • 30-45

Use this for something near you. For example, say: I like this apple in my hand.

Teacher holds an apple close to their chest in high teacher presence, with clean text overlay 'This = Near' in the upper screen area.

TEACH • 45-60

Use that for something farther away. For example, say: Look at that plane in the sky.

Teacher points toward the background across the room with readable text overlay 'That = Far' above the lower subtitle zone.

TEACH • 60-75

This also works for current moments, while that is for past moments or ideas that feel farther away.

Clean graphic illustration showing a timeline with 'This week' placed close and 'That day' placed in the distance.

CTA • 75-90

Parents, follow our page for more easy English tips for your child.

Teacher smiles warmly at the camera with clear lower-third text overlay displaying 'Follow for English lessons'.

Figure 7. Completed Content Pack.

03 / CONTROLLED BETA

Platforms, Formats and Recommendations

Use the supported platform and format options currently shown in the Create interface unless an item is explicitly marked Preview.

- Platform choice influences TeacherFly recommendations such as content format and duration.
- Use recommendations as a starting point. Available supported controls remain visible so you can choose an appropriate option.
- Platform guidance and generation ranges can change as Beta profiles are validated.




Figure 8. Platform-specific recommendation displayed in the Create workflow.




Figure 9. Recommended duration for the selected format.

04 / CONTROLLED BETA

Audience, CEFR and Grammar Mode

These controls help TeacherFly adapt the generated content to the intended learner.

Learner age

Choose the audience that best matches the people you teach. The app includes choices such as Children, Teenagers and Adults.

Figure 10. Learner Age control.

CEFR level

For language teaching, CEFR controls the expected vocabulary, grammar, lesson difficulty and pedagogical level. Select the level that best matches the intended learner.

Figure 11. CEFR Level control.

Grammar Mode

- **Natural:** Conversational/everyday English with natural phrasing appropriate to the selected learner level.
- **Strict:** More rigorous control of grammar and structures; useful for exam preparation or lessons where explicit grammatical accuracy is important.

Figure 12. Natural and Strict Grammar Mode controls.

05 / CONTROLLED BETA

Tone, Hook and CTA

Tone controls teacher personality; Hook controls the opening; CTA (Call-to-Action) controls the ending or viewer prompt.

Tone

Some tones are restricted or unavailable for Children in Natural mode.




Figure 13. Tone selector.




Figure 14. Example of a Child audience tone restriction.

Hook styles

- Myth Buster — challenges a common misconception.
- Secret/Shortcut — introduces a useful shortcut or lesser-known insight.
- Big Question — opens with a question designed to make the learner think.
- Story Hook — starts with a short situation or narrative.
- Niche-Specific — speaks directly to a defined learner or audience.
- Warning — highlights a mistake, risk or something to avoid.




Figure 15. Hook Style selector.

CTA styles

- Free Worksheet
- Leave a Comment
- Free Trial Class
- Follow/Subscribe
- Share with Friends/Parents
- Save Post
- Click for Next Lesson
- Ask a Question

Adaptive wording TeacherFly adapts the exact wording of hooks and CTAs to the selected audience and content context.




Figure 16. CTA Style selector.

Subtitles and Translation

Choose one Subtitle Language option for each Content Pack. Bilingual options generate bilingual subtitle content.

- TeacherFly produces one SRT file for the pack.
- The exact bilingual wording can vary because translation is generated as part of the content workflow.
- Advanced Settings can add learner First Language, Cultural Adaptation and a Custom Note when useful for the lesson.



Figure 17. Subtitle Language selector.




Figure 18. Advanced Settings control.




Figure 19. Additional learner and cultural adaptation controls.

07 / CONTROLLED BETA

Understanding Your Content Pack

A completed pack brings the primary content and supporting social-media assets together in one workflow.

- Content Title
- Script / scenes
- Subtitles
- SEO Pack: SEO Title, Description, Caption and Hashtags
- Worksheet
- Visual Directions

Title distinction Content Title identifies the item in TeacherFly. SEO Title belongs to the SEO Pack and is intended for publishing/search use.

The screenshot displays the TeacherFly interface for a content pack. On the left, a sidebar contains navigation links: Create, Batch Studio, Content Library, Resources, User Guide, and Settings. Below these are usage statistics: Credits Used (188 / 443), Total Packs Created (497), Library Storage (9 / 20), Video Content Created (7m), and Total Slides Created (19). The main area shows a content pack with a header bar indicating settings like Subject (General English), Age (Children (8-12)), Level (A2 Elementary), Grammar (Natural), Platform (YouTube), Format (Short Video), Duration (90s), Tone (Friendly & Encouraging), Hook (Secret/Shortcut), and CTA (Free Trial Class). Below the header is a 'Regenerate with same settings' button. The content pack is organized into sections: Hook (0-15), Teach (15-30), Teach (30-45), Teach (45-60), Teach (60-75), and CTA (75-90). Each section includes a script and visual directions. The right sidebar shows 'Monthly Creation Trends' and 'Downloads & Exports' options.

Figure 20. Full Content Pack view.




Figure 21. Script scene with teaching text and visual direction.




Figure 22. Copy individual Content Pack assets.

Worksheets and Downloads

TeacherFly worksheets are designed for student self-practice and self-assessment. Use the worksheets to offer value to your audience or to attract them to your landing page / offer.




Figure 23. Worksheet preview.

Download options

Available downloads can include TXT files, an SRT subtitle file and Download All (ZIP). A downloaded ZIP may contain:

- script.txt
- seo-pack.txt
- subtitles.srt
- visual-directions.txt
- worksheet.txt

Tip Use individual download buttons when you only need one asset. Use Download All (ZIP) when you want the complete export set.




Figure 24. Download and export actions.

Name	Type	Compressed size	Password ...	Size
script.txt	Text Document	1 KB	No	
seo-pack.txt	Text Document	1 KB	No	
subtitles.srt	GOM Media file(.srt)	2 KB	No	
visual-directions.txt	Text Document	1 KB	No	
worksheet.txt	Text Document	2 KB	No	

Figure 25. Example downloaded files.

08 / WORKSHEETS & DOWNLOADS

Single Pack Worksheet status

Single Pack can generate a Worksheet automatically after its Content Pack is saved. A successful pack remains available even when Worksheet generation fails.

CONTENT PACK

Script Preview

Worksheet **Ready** **View** **Hide preview**

HOOK • 0-6
States of Matter Can you spot the difference between ice, water, and steam?
Vertical still layout showing three clear jars containing an ice cube, liquid water, and rising steam with clean text.

TEACH • 6-12
Ice and Water Ice is a solid because it keeps its shape. Water is a liquid that flows and pours.
Vertical split comparison showing a solid ice cube resting on a plate beside liquid water pouring into a cup.

TEACH • 12-18
Steam Is Gas Steam is a gas. Unlike ice and water, gas spreads out to fill any space around it.
Vertical still illustration of a teapot releasing visible steam into the air with clear text overlay reading Gas.

TEACH • 18-24
Three Simple States Solids hold shape, liquids flow into cups, and gases spread freely everywhere.
Vertical three-column summary card displaying ice, water, and steam side by side with simple property labels.

CTA • 24-30
Save for Later Parents, save this carousel to review science ideas together.
Minimalist vertical end card with a fixed bookmark graphic and subtitle-safe text inviting parents to save the post.

Copy SEO Pack **Copy Slides** **Copy Alt Text** **Copy Worksheet** **Copy Visual Directions**

U06. A successful Content Pack preview with its own Worksheet status and View control.

- In Batch Studio, Worksheets are created separately from each ready pack's Preview. The unavailable U07 example is intentionally omitted.
- Worksheet generation and retries belong to the saved pack, not a previously opened preview.

09 / CONTROLLED BETA

Library and Teleprompter

Save Content Packs for reuse and move video scripts directly into the Teleprompter.

Content Library

- The Library keeps saved Content Packs with their generation settings, a script preview and copy/download actions.
- Selecting Open returns the saved pack to the Create view with its saved configuration available.
- Delete only packs you no longer need. The delete confirmation is permanent for that saved Library item.
- Use Multi-Delete when you want to select and remove more than one saved Library item at a time.




Figure 26. Content Library.

READY TO GENERATE WITH:

Subject: **Business English** • Age: **Adults (18+)** • Level: **B1 Intermediate** • Grammar: **Natural** • Platform: **FB Reels** • Format: **Short Video** • Duration: **90s** •

Tone: **Energetic** • Hook: **Big Question** • CTA: **Follow/Subscribe** • Subtitle: **Portuguese + English** • First Language: **None** • Cultural Adaptation: **Neutral (Global)**

Regenerate with same settings

Copy Title Copy Script Copy Subtitles Copy Caption Copy Description # Copy Hashtags Copy Worksheet Copy Visual Directions

Copy timestamped subtitles

Repurpose **PREVIEW**

HOOK • 0-18

Are you accidentally sabotaging your team by giving vague feedback during performance reviews?

Close-up of a concerned teacher looking directly into the lens, high-energy framing.

TEACH • 18-36

Effective feedback is specific, actionable, and supportive. It moves away from personal criticism toward clear, professional improvement. This ensures your team feels valued and understands exactly how to grow.

Split screen showing a person looking confused versus a person looking motivated during a talk.

Figure 27. Reopened Library item.

3 selected **Delete Selected** Cancel

Batch Creations

Available once Batch Studio is released. Manage, organize and download all your batch-created content packs from one place.

when to use 'this' and when to use 'that' ☒

FB Reels A2 Elementary Short Video L1:Portuguese

Global Portuguese

9/27/2026 • 6 scenes

Open Repurpose **PREVIEW** Delete

Should I use 'some' or 'any'? ☒

Instagram A2 Elementary Short Video

L1:Chinese(Mandarin) Light Chinese

9/26/2026 • 4 scenes

Open Repurpose **PREVIEW** Delete

Should I use some or any? ☒

FB Reels A2 Elementary Short Video L1:Spanish

Global Spanish

9/25/2026 • 6 scenes

Open Repurpose **PREVIEW** Delete

Using prepositions of place ☐

FB Reels A2 Elementary Short Video L1:None

Global Italian

9/25/2026 • 6 scenes

Open Repurpose **PREVIEW** Delete

Figure 28a. Multi-Delete selection in the Content Library.

teacherfly.app says

Delete this pack? This cannot be undone.


OK Cancel

Figure 28b. Permanent delete confirmation.


09 / CONTENT LIBRARY

Find packs, Worksheets and assets

Use Library search and the pack-type dropdown to find Single Packs, Batch-created packs, packs containing Worksheets, packs containing Repurpose assets, or packs without these assets. The search, level, platform and style filters can be combined.



U04. Content Library with the current filter controls and saved packs.



U05. Saved pack details and its Worksheet / Repurpose labels.

- A Worksheet label represents an available saved Worksheet; opening a pack does not create a new Worksheet.

Teleprompter

- Play / Pause
- Speed control
- Text color: Indigo, White or Coral
- A– / A+ font size controls
- Horizontal mirror
- Dark / Light mode
- Reset




Figure 29. Teleprompter in use.

Account, Settings, Credits and Storage

Open Settings to review account information, default creation preferences, appearance and usage.

Settings
Manage your account, default creation preferences, appearance and displayed activity statistics.

Account

NAME: Test Teacher

EMAIL: test@teacherfly.com

[Send Password Reset Email](#)

Default Creation Preferences
These defaults apply to a fresh Content Creator form. They never replace settings restored from a saved Library pack.

DEFAULT PLATFORM FB Reels	DEFAULT SUBTITLE LANGUAGE English only	DEFAULT SUBJECT Business English
DEFAULT LEARNER AGE Adults (18+)	DEFAULT CEFR LEVEL B1 Intermediate	DEFAULT TONE Friendly & Encouraging
DEFAULT HOOK STYLE Secret/Shortcut	DEFAULT CTA Follow/Subscribe	DEFAULT GRAMMAR MODE Natural

Appearance

☒ Light mode ☐ Dark mode

Figure 30. Settings screen.

Credits

TeacherFly deducts a generation credit after a Content Pack is successfully generated and delivered. A failed or rejected generation that returns no complete pack should not consume a generation credit.

Beta credit policy This guide does not promise a fixed credit reset schedule. Use the usage counter shown in TeacherFly to see your current account usage.



Figure 31a. Account usage display.

Library capacity

TeacherFly displays Library usage/capacity in the interface. If the Library becomes full, download anything you want to keep and remove older saved packs before saving another one.



Figure 31b. Content Library capacity counter.

10 / ACCOUNT & SETTINGS

Profile and account security

Use Account Settings to review your account name and email, upload or replace a profile photo or logo, and manage password recovery. Use the eye controls on password inputs when you need to verify typed characters.

Account Settings

Manage your profile, account, default creation preferences, appearance and displayed activity statistics.

Account



Profile photo or logo
Personalize your TeacherFly welcome screen. JPG, PNG or WebP - maximum 2 MB.

[Upload image](#) [Remove image](#)

NAME

Test Teacher

[Send Password Reset Email](#)

EMAIL

test@teacherfly.com

Default Creation Preferences

These defaults apply to a fresh Content Creator form. They never replace settings restored from a saved Library pack.

DEFAULT PLATFORM	DEFAULT SUBTITLE LANGUAGE	DEFAULT SUBJECT
FB Reels	English only	Business English
DEFAULT LEARNER AGE	DEFAULT CEFR LEVEL	DEFAULT TONE
Adults (18+)	B1 Intermediate	Friendly & Encouraging
DEFAULT HOOK STYLE	DEFAULT CTA	DEFAULT GRAMMAR MODE
Secret/Shortcut	Follow/Subscribe	Natural

Informational and interactive pop-up messages

Optional messages can include "Do not show this message again". Required security, billing, deletion, credit and upgrade information will always be shown.

☒ **Enable** (default) ☐ **Disable**

Saved to your account.

[Preview informational pop-up](#) [Reset dismissed tips](#)

To test: Enable → Preview informational pop-up → tick "Do not show this message again" → OK → Preview again. Use Reset dismissed tips to repeat. Required billing, account and credit prompts are not affected.


U01. Profile, account details, and password-change controls.

- To change a password, begin with the secure reset email, then follow the recovery instructions.

10 / ACCOUNT & SETTINGS

Account deletion and verification

Deleting an account permanently removes TeacherFly account data and saved content. Subscription cancellation and account deletion are different actions. Read the warnings before confirming an irreversible deletion.



Delete Account

Permanent account deletion removes your TeacherFly account, saved Library packs and files, account profile, creation activity, quota records and generation telemetry. This cannot be undone.


Type **DELETE MY ACCOUNT** to confirm

DELETE MY ACCOUNT

Delete My Account Permanently

U02. Initial Delete Account panel and confirmation requirements.

If a previous deletion was initiated but could not be verified, TeacherFly can offer Resume Deletion Verification. This is not triggered merely by cancelling a subscription. Confirm the continuation through its separate prompt; do not repeatedly initiate deletion.



Your TeacherFly account has been deleted successfully. Your subscription has been canceled and your saved account content removed. A confirmation email will be sent to your registered address.


By signing in or using TeacherFly, you agree to the [Terms of Service](#) and acknowledge the [Privacy Policy](#).

U03. Notice and confirmation state for a previous deletion request.

- If deletion confirmation is delayed, allow up to 24 hours for support verification and contact support@teacherfly.app if the account remains accessible.
- A completed deletion should display a success acknowledgement after redirect. Account deletion cannot be undone.

Default creation preferences

Set defaults for commonly used options such as platform, language, subject, learner age, CEFR level, tone, hook, CTA and Grammar Mode. You can still change settings for an individual pack.



Default Creation Preferences


These defaults apply to a fresh Content Creator form. They never replace settings restored from a saved Library pack.

DEFAULT PLATFORM	DEFAULT SUBTITLE LANGUAGE	DEFAULT SUBJECT
FB Reels	English only	Business English
DEFAULT LEARNER AGE	DEFAULT CEFR LEVEL	DEFAULT TONE
Adults (18+)	B1 Intermediate	Friendly & Encouraging
DEFAULT HOOK STYLE	DEFAULT CTA	DEFAULT GRAMMAR MODE
Secret/Shortcut	Follow/Subscribe	Natural

Figure 32. Editable default creation preferences.

Password and account deletion

Password reset is available from the sign-in/account flow. Account deletion is permanent. TeacherFly requires the exact confirmation phrase shown in Settings and a browser confirmation before deletion proceeds.



Delete Account

Permanent account deletion removes your TeacherFly account, saved Library packs and files, account profile, creation activity, quota records and generation telemetry. This cannot be undone.


Type **DELETE MY ACCOUNT** to confirm

DELETE MY ACCOUNT

Delete My Account Permanently

Save Settings

Figure 33. Delete Account control.



teacherfly.app says

Permanently delete your TeacherFly account and all associated TeacherFly account data? This cannot be undone.

OK Cancel

Figure 34. Final browser confirmation.

11 / BATCH STUDIO

Batch Studio: Create a Batch

Batch Studio creates several Content Packs from separate topics using shared settings. A batch requires at least two topics. Access depends on your plan.

Create Your Content Pack

Single Pack **Batch Mode**

Include Worksheet Yes No

CONTENT TOPICS (ONE PER LINE)

IELTS Speaking Part 2
Business English: Presentations
TOEFL Listening Tips

0 topics • 2-5 topics per batch

Batch Mode selected on the Create page.

Create Your Content Pack

Single Pack **Batch Mode**

Include Worksheet Yes No

CONTENT TOPICS (ONE PER LINE)

Three examples of prepositions of position
Using 'in' or 'at' or 'on' correctly when talking about time and locations
Common mistakes made when using prepositions of time

3 topics • 2-5 topics per batch

Enter one topic per line. Review the topic count before generating.

Select Subject, Age, CEFR, Grammar Mode, platform, format, duration, tone, hook, CTA and subtitle language. The selected settings apply to every topic in the batch.

Create Your Content Pack

Single Pack **Batch Mode**

Include Worksheet Yes No

CONTENT TOPICS (ONE PER LINE)

Three examples of prepositions of position
Using 'in' or 'at' or 'on' correctly when talking about time and locations
Common mistakes made when using prepositions of time

3 topics • 2-5 topics per batch

AUDIENCE

SUBJECT: General English LEARNER AGE: Teenagers (13-17) CEFR LEVEL: A2 Elementary

GRAMMAR MODE

Natural Strict

CONTENT STRATEGY

PLATFORM: YouTube CONTENT FORMAT: Short Video DURATION / SLIDES: 90s

CONTENT STYLE

TONE: Friendly & Encouraging HOOK STYLE: Big Question CTA STYLE: Follow/Subscribe

SUBTITLE LANGUAGE: Spanish + English

Advanced Settings

READY TO GENERATE WITH:

Subject: General English Age: Teenagers (13-17) Cultural Adaptation: Neutral (Global) Worksheet

TeacherFly Controlled Beta | 26

Generate Batch (3 packs)

11 / BATCH STUDIO

Batch Studio: Progress and Retry

Select Generate Batch and follow each topic in the three-row progress panel. Topics run sequentially. A ready pack remains intact if another topic fails.

READY TO GENERATE WITH:

Subject: **General English** * Age: **Teenagers (13-17)** * Level: **A2 Elementary** * Grammar: **Natural** * Platform: **YouTube** * Format: **Short Video** * Duration: **90s** *
Tone: **Friendly & Encouraging** * Hook: **Big Question** * CTA: **Follow/Subscribe** * Subtitle: **Spanish + English** * First Language: **None** * Cultural Adaptation: **Neutral (Global)**
* Worksheet: **No**

▶ Generate Batch (3 packs)

Batch creation

Processing 3 topics with your current settings.

Cancel Batch

... 1. Three examples of prepositions of position

Generating...

• 2. Using 'in' or 'at' or 'on' correctly when talking about time and locations

Waiting

• 3. Common mistakes made when using prepositions of time

Waiting

CONTENT PACK

Script Preview

Hide preview

TeacherFly is creating your content

Generating 1/3: Three examples of prepositions of position...

Copy SEO Pack

Copy Script

Copy Subtitles

Copy Worksheet

Copy Visual Directions

Generating one topic while the other rows remain visible.

Ready: Preview or Download ZIP. Failed: Retry that topic within the available limit. Generating: wait for progress; do not send a second request.

✓ Batch complete: 2 packs ready • 1 failed

Download All as ZIP

View in Batch Studio

▶ Generate Batch (3 packs)

Batch topics — progress and retry

Processing 3 topics with your current settings.

✓ 1. Three examples of prepositions of position

Ready

Preview

Download ZIP

✓ 2. Using 'in' or 'at' or 'on' correctly when talking about time and locations

Ready

Preview

Download ZIP

! 3. Common mistakes made when using prepositions of time

Failed: WHOLE_CANDIDATE_TRANSLATION_REJECTED

Retry

CONTENT PACK

Script Preview

Worksheet Ready View

Hide preview

Batch topic 3 could not be completed

Generation could not be completed. Please try again.

No pack was saved. Your settings were preserved.

Copy SEO Pack

Copy Visual Directions

11 / BATCH STUDIO

Batch Studio: Completed Packs

When the batch finishes, use Download All as ZIP or View in Batch Studio. Some packs may succeed while others remain available for individual retry.

The screenshot shows the Batch Studio interface. At the top, there are two buttons: "Download All as ZIP" (dark blue) and "View in Batch Studio" (orange). Below these is a "Generate Batch" button with a play icon. The main section is titled "Batch creation" and shows "Processing 3 topics with your current settings." A "Batch finished" status is indicated in the top right. Three topics are listed:

- 1. Three examples of prepositions of position: Failed: WHOLE_CANDIDATE_TRANSLATION_REJECTED. Retry button.
- 2. Using 'in' or 'at' or 'on' correctly when talking about time and locations: Failed: WHOLE_CANDIDATE_TRANSLATION_PROVIDER_FAILED. Retry button.
- 3. Common mistakes made when using prepositions of time: Ready. Open and Download ZIP buttons.

At the bottom, there is a "CONTENT PACK" section with a "Script Preview" button. To the right, there are buttons for "Worksheet" (with a document icon), "Ready", "View", and "Hide preview".

Batch completion summary, successful packs and failed-pack retry.

Worksheets for Batch packs are created manually after pack generation. Open Preview for a ready pack, then use Worksheet > Create. A failed pack cannot have a new Worksheet until its Content Pack is ready.

The screenshot shows the Batch Studio interface for a specific batch. The header includes "TEACHERFLY BATCH STUDIO" and a "FOLDERS 4 / 15" indicator. The main section is titled "Batch Creations" and explains that each batch is saved as a dated folder. Below this is a search bar and filters for "All Levels", "All Platforms", "All Formats", and a "Clear" button. The "FOLDER PACKS" section shows a list of packs for the folder "Oct 21, 2026, 11:46 PM". The packs are:

- 1. Three examples of prepositions of position: Content Pack ready. Open, Pack ZIP, Regenerate, View in Library, Repurpose, Delete buttons.
- 2. Using 'in' or 'at' or 'on' correctly when talking about time and locations: Content Pack ready. Open, Pack ZIP, Regenerate, View in Library, Repurpose, Delete buttons.
- 3. Common mistakes made when using prepositions of time: Content Pack ready. Open, Pack ZIP, Regenerate, View in Library, Repurpose, Delete buttons.

Batch Studio folder and pack cards. Use Preview, Pack ZIP, Regenerate and Library actions as available.

11 / BATCH STUDIO

Batch Preview, Worksheets and Assets

Open a completed Batch pack in Preview. Select another ready pack to change the script and its Worksheet/Repurpose state without regenerating anything.

The screenshot displays the TeacherFly Batch Studio interface. At the top, there is a search bar and filters for 'All Levels', 'All Platforms', and 'All Formats'. Below this, a section titled 'FOLDER PACKS' shows a button for 'All batch folders'. The main content area displays a batch pack for 'Oct 22, 2026, 06:48 AM' with details: 'General English • A2 Elementary • Children (6-12) • Short Video • YouTube'. The batch status is 'complete' with '3/3 ready'. Three content packs are listed:

- 1. Three examples of prepositions of position**: Content Pack ready. Buttons: Preview, Pack ZIP, Regenerate, View in Library, Repurpose, Delete.
- 2. Using 'in' or 'at' or 'on' correctly when talking about time and locations**: Content Pack ready. Buttons: Preview, Pack ZIP, Regenerate, View in Library, Repurpose, Delete.
- 3. Common mistakes made when using prepositions of time**: Content Pack ready. Buttons: Preview, Pack ZIP, Regenerate, View in Library, Repurpose, Delete.

The 'Script Preview' section for the first pack is expanded, showing a 'Close preview' button. The script includes:

- HOOK • 0-15**: Learn one easy trick to choose the right position word every time. (Vertical 9-16 framing. Friendly teacher smiles at camera with animated text overlay 'Position Words' appearing in upper center.)
- TEACH • 15-30**: Position words clearly show where objects are. Use in for inside a space. The ball is in the box. (Vertical 9-16 shot. Teacher places a red ball inside a small wooden box, with clean graphic text 'IN = INSIDE'.)
- TEACH • 30-45**: Next, use on when an object touches the top of something. For example, the book is on the desk. (Vertical 9-16 medium shot. Teacher sets a blue book onto the flat surface of a desk, displaying keyword highlight 'ON'.)
- TEACH • 45-60**: Then, use under when an object is lower than something else. For example, the dog is under the bed. (Vertical 9-16 angle. Teacher points down to a toy dog resting beneath a small toy bed, with animated label 'UNDER'.)
- TEACH • 60-75**: Look closely at the object and its place. That helps you choose in, on, or under every time. (Vertical 9-16 three-panel graphic review displaying the ball in the box, book on the desk, and dog under the bed.)
- CTA • 75-90**: Parents, subscribe for more gentle English lessons to help your child. (Vertical 9-16 shot. Teacher smiles calmly to camera, gesturing toward a clean graphic banner reading 'Subscribe for English Lessons'.)

At the bottom, the 'Worksheet' status is 'Ready' with a 'View' button.


Batch folder preview with selected script and its own saved pack data.

- Worksheet status can be Not requested, Generating, Ready, Failed or Unavailable. Use Create, View or Retry only when offered for the selected pack.
- Preview does not generate or charge for a new pack. Regenerate Batch creates a new batch using the restored settings; changing settings restores the normal Generate Batch action.
- Repurpose and saved Worksheet data belong to the selected pack, not to whichever pack was previewed previously.


12 / REPURPOSE CONTENT

Repurpose: Start from a Pack


Repurpose creates a new asset based on an existing, successfully generated Content Pack. The original script is kept unchanged. Availability varies by plan.



Repurpose from a saved Content Library pack.



Repurpose from the Content Pack preview.




Repurpose asset selection preview.


12 / REPURPOSE CONTENT

Repurpose: Generate and Review

Choose an available asset type. Review its title and instructions, then select Create. The progress state indicates that the asset is being produced; do not submit another request while it runs.



Asset generation in progress.



Generated asset preview and available Copy, Download, Replace or Delete actions.

12 / REPURPOSE CONTENT

Repurpose: Saved Assets

Repurposed assets remain associated with their source Content Pack. Return through Content Library or the pack preview to access them.

Common mistakes made when using prepositions of time

Subject: General English	Age: Teenagers (13-17)
Level: A2 Elementary	Grammar: Natural
Platform: YouTube	Format: Short Video
Duration: 90s	Tone: Friendly & Encouraging
Hook: Big Question	CTA: Follow/Subscribe
Subtitle: Spanish + English	First Language: None

10/22/2026 • 6 scenes

 **Worksheet**

 **Batch created**

 **Repurposed asset**

 **Open**

 **Repurpose**

 **Delete**

A Content Library item showing its Repurposed asset label.

Good practices

- Review accuracy, learner suitability, call-to-action language and formatting before publishing.
- Replacing or editing a CTA may leave previously generated subtitles or SRT with the old wording; check subtitles before publishing.
- Repurpose actions may use credits or plan allowances. Check the current Account Usage page for your entitlement.
- A failed asset should display the available Retry action, if permitted; do not repeatedly submit while a request is in progress.

13 / MY PLAN & BILLING

Compare and choose a plan

Free, Explorer, Solo Flyer and Creator plans

Open My Plan & Billing from the sidebar. The My plan & upgrades tab identifies the signed-in account holder, current subscription and available plans.

Switch between Monthly and Annual to compare prices. Confirm the final amount displayed by Paddle at checkout; taxes and currency conversion can affect the charge.

TEACHERFLY ACCOUNT

My Plan & Billing

Manage your plan, track credit usage and open secure Paddle billing controls.

[My plan & upgrades](#) [Account Usage](#) [Manage Billing](#)

CURRENT ACCOUNT
Account holder: test@teacherfly.com

Solo Flyer Plan
Monthly billing.

Monthly **Annual** [Save more](#)

Display currency: **USD — US Dollar**

Displayed prices use Paddle pricing previews in USD. The final checkout amount, including applicable tax, is shown by Paddle.

TRY TEACHERFLY	BUILD AN ONLINE PRESENCE	BUILD YOUR AUDIENCE	GROW YOUR TEACHING BUSINESS
Free \$0.00 For teachers who want to try TeacherFly before committing to a paid plan.	Explorer \$9.00 / month Save 18% with annual billing For teachers who want an affordable way to start building an online presence.	Solo Flyer \$17.00 / month Save 18% with annual billing For teachers and tutors building their teaching business and attracting private students.	Creator \$29.00 / month Save 17% with annual billing For experienced teachers growing their student base while spending less time creating marketing content.
✓ 10 Content Pack Credits ✓ Student Worksheets ✓ SEO Packs ✓ Subtitle Files ✓ Visual Directions ✓ Teleprompter ✓ Content Library: 10 packs ✓ Limited Access to Resources	✓ 25 Content Pack Credits ✓ Credit top-ups ✓ SEO Packs ✓ Student Worksheets ✓ Subtitle Files ✓ Visual Directions ✓ Teleprompter ✓ Content Library: 20 packs ✓ Unlimited Access to Resources ✓ Monthly Creation Trends	✓ 60 Content Pack Credits ✓ SEO Packs ✓ Student Worksheets ✓ Subtitle Files ✓ Visual Directions ✓ Teleprompter ✓ Content Library: 50 packs ✓ Unlimited Access to Resources ✓ Monthly Creation Trends ✓ Batch Studio: 3 / month ✓ Repurpose: 15 / month	✓ 150 Content Pack Credits ✓ SEO Packs ✓ Student Worksheets ✓ Subtitle Files ✓ Visual Directions ✓ Teleprompter ✓ Content Library: 120 packs ✓ Unlimited Access to Resources ✓ Monthly Creation Trends ✓ Batch Studio — Unlimited ✓ Repurpose — Unlimited ✓ Early access / trials to new functions
Cancel paid plan	Change to Explorer	Current Plan	Upgrade to Creator

Figure P01. Plan comparison and the current plan indicator. Plan availability and prices displayed in your account govern.

13 / MY PLAN & BILLING

Review credits and usage

Billing-period allowance, usage and top-up credits

Select Account Usage to review credits used, credits remaining, Content Pack generations and Repurpose generations for the current billing period.

Your subscription credits and purchased top-up credits are displayed separately. Batch and Repurpose allowances can be subject to plan limits. A failed attempt that produces no completed pack should not consume a Content Pack generation credit.

TEACHERFLY ACCOUNT

My Plan & Billing

Manage your plan, track credit usage and open secure Paddle billing controls.

[My plan & upgrades](#)[Account Usage](#)[Manage Billing](#)

CURRENT ACCOUNT

Account holder: test@teacherfly.com

Solo Flyer Plan

Monthly billing.

ACCOUNT USAGE

Your current billing period

Oct 9, 2026 – Nov 9, 2026

Credits used

84

this billing period

Credits remaining

9

0 subscription + 9 top-up

Content Pack generations

67

successful billed generations this period

Repurpose generations

17

13 new assets + 4 replacements

Batch Studio allowance

2 of 3 Batch creations remaining

New Repurpose asset allowance

2 of 15 new assets remaining

Credits and feature allowances are separate. Every successful Repurpose generation costs 1 credit, while the monthly Repurpose allowance counts only **new** assets; replacements/regenerations do not use another allowance slot.

NEED MORE CAPACITY?

Grow without interrupting your workflow.

Upgrade your plan for a larger monthly allocation, or add top-up credits to an active paid subscription.

[View upgrade options](#)

[Buy Top-up Credits](#)

Figure P02. Account Usage. Numbers shown are from the example test account and are not fixed plan allowances.

TeacherFly Controlled Beta | Billing & Upgrades

30



13 / MY PLAN & BILLING

Upgrade or change plans

Review charges before authorizing a plan change

Choose an available plan. For a change that takes effect immediately, TeacherFly displays a Paddle proration preview. The saved payment method may be charged when you select Authorize Payment of New Plan.

Check the new charge, unused-plan credit and amount due today. After the payment is verified, TeacherFly displays the successful plan change. Do not submit the same authorization repeatedly.



Figures P03a-P03b. Immediate plan change authorization and successful confirmation. Monthly-to-annual or other scheduled changes may instead take effect at the next billing date; follow the effective date displayed in your account.



13 / MY PLAN & BILLING

Purchase additional credits

Choose a top-up and complete secure Paddle checkout

Where your plan permits top-ups, select Buy Top-up Credits. The example shows \$1 base unit = 3 additional Content Pack credits. Choose the amount, then review Paddle checkout.

Paddle handles payment and any applicable tax. After a successful purchase, TeacherFly verifies the transaction and adds the credits. Avoid repeating checkout while verification is pending.



Figures P04-P05. Top-up selection and Paddle checkout. The displayed amount and taxes are examples, not a quote for your purchase.

13 / MY PLAN & BILLING

Manage billing and cancellation

Payment methods, invoices and subscription controls

Open the Manage Billing tab to access Paddle controls for your payment method, invoices and billing details. TeacherFly also displays the current subscription and its renewal information.

To cancel, use the subscription cancellation control and review the confirmation. Scheduled changes and cancellations must be checked for their stated effective date. Billing cancellation does not delete your TeacherFly account.

TEACHERFLY ACCOUNT

My Plan & Billing

Manage your plan, track credit usage and open secure Paddle billing controls.

My plan & upgrades Account Usage **Manage Billing**

CURRENT ACCOUNT
Account holder: test@teacherfly.com

Creator Plan
Monthly billing.

MANAGE BILLING

Secure billing managed by Paddle

TeacherFly does not store your full card details. Use Paddle's secure billing portal to update payment methods, billing details and invoices.

Payment method
Update the card or other payment method attached to your TeacherFly subscription.

[Update payment method ↗](#)

Billing information & invoices
Review billing details, invoice history and tax information securely in Paddle.

[Open billing & invoices ↗](#)

SUBSCRIPTION SUMMARY

Creator Plan

Status	Billing cycle	Next billing date
Active / current	Monthly	Nov 9, 2026

[Upgrade Plan](#) [Cancel subscription](#)

Figure P06. Manage Billing and the subscription summary.

Refunds: The introductory seven-day money-back guarantee is subject to the published Refund Policy and historical eligibility. It does not automatically restart with a newly created account. Statutory rights are unaffected.

For billing problems, use support@teacherfly.app. Do not share full card numbers or account passwords with support.

Troubleshooting

Use the same bounded troubleshooting pattern for most Beta issues: try again up to 3 times, check settings if relevant, then report the problem if it continues.

Universal Beta rule Try again up to 3 times → check settings if relevant → report the problem if the same issue continues. Do not keep generating the same request indefinitely.

Quality Block / no pack returned

Select Generate Again. Retry the same request up to 3 times. If it still fails, review settings if relevant and Report Problem. A failed Quality Block that delivers no complete pack should not consume a credit.

Settings / request problem

Select Check Settings. Review the Topic and selected options, correct anything needed, then Generate Again. Report the problem if it continues after up to 3 attempts.

Provider / AI service error

Wait briefly, then Try Again. Retry up to 3 times. If the service problem continues, Report Problem.

TeacherFly / server error

Try Again up to 3 times. If the same error returns, Report Problem.

Login / session expired

Sign In Again. If necessary, sign out completely and sign back in. If access still fails, contact support.

No credits remaining

Check Credits. Do not keep retrying generation. Follow the Beta access instructions shown in TeacherFly or contact support if the credit count looks incorrect.

Library / storage full

Manage Library. Download packs you want to keep, remove older saved packs, then save again.

Download problem

Try the download again. If Download All fails, download the individual assets you need. Report the problem if it continues.

Repeated / unknown error

Stop retrying and Report Problem. Include a Request ID if TeacherFly shows one.




Figure 37. Example generation error state.




Figure 38. Example sign-in error.




Figure 39. Sign-in required state.


Network / browser checks

If TeacherFly appears unresponsive, confirm that your internet connection is working and refresh the page once. If the same issue continues after the normal retry steps, report it instead of repeatedly refreshing or generating.


14 / TROUBLESHOOTING

Generation and Worksheet recovery

A failed Content Pack and a failed Worksheet have independent statuses. Retry only the failed operation and avoid starting duplicate requests while a generation is still in progress.



U08. Content Pack failure with the available Retry action.



U09. Worksheet Unavailable: the three-attempt limit has been reached; the saved Content Pack is still usable.

- For failed Content Packs, check the error and use Retry if available. Previously completed Batch packs do not need to regenerate.
- For Worksheet Failed, use its own Retry. Worksheet Unavailable means the retry limit has been exhausted; do not repeatedly click generation elsewhere.
- When reporting a repeated failure, include the topic, settings, error status and relevant screenshots; never share a password or payment details.

Beta Feedback and Support

TeacherFly Controlled Beta depends on tester feedback. If a problem persists, report what happened as clearly as possible.

Support support@teacherfly.app

When reporting a problem, include

- what you were trying to do
- what happened instead
- the steps that led to the problem
- a screenshot when useful
- the Request ID, if TeacherFly shows one
- browser/device information when relevant

For generation-quality feedback

You can also mention the Platform, Format, CEFR, Learner Age, Grammar Mode, Tone, Hook and CTA selections that were used.

Privacy reminder Do not include identifiable student/minor personal information or sensitive personal information in a feedback report.

Suggested feedback categories

- Bug
- Generation quality
- Usability / confusing UI
- Feature suggestion
- Other

If an in-app Beta Feedback / Report Problem option is available, use it. If it is not visible, email support@teacherfly.app.

TeacherFly

Spend less time creating social media and marketing content. Spend more time focused on your teaching.

16 / MOBILE INSTALLATION


Install TeacherFly on your phone

Android phone / Chrome - steps 1 and 2

Use the official teacherfly.app website. This installs the Progressive Web App (PWA); the screens below are from an Android phone, so menu wording may vary by browser.

1 Visit teacherfly.app


Open your phone browser and enter teacherfly.app in the address bar.



Find the website address at the top.

2 Open the browser menu

Once TeacherFly opens, tap the three-dot menu near the top-right.



Look for the three dots circled in yellow.


16 / MOBILE INSTALLATION

Install TeacherFly on your phone

Android phone / Chrome - steps 3 and 4

3 Choose installation


In the browser menu, select Install and create shortcut.



The install option is highlighted in yellow.

4 Select Install

Choose Install, rather than Create shortcut.



Select the first option in the bottom sheet.


16 / MOBILE INSTALLATION

TeacherFly is ready to launch

Android phone / Chrome - steps 5 and 6

5 Confirm the app


When the TeacherFly Install app dialog appears, tap Install.



Check the TeacherFly name and logo.

6 Open TeacherFly

Find the TeacherFly icon on your phone screen and tap to launch it.



Your phone can now open TeacherFly like an app.

If Install is missing, open the site directly in Chrome and check the browser menu again.